


WP-523x CE 7.0 OS 1.0.1.4 Release Notes

Release Date: 03/20/2017


Key Features:

Features	Supported	Description
Windows CE 7.0 Core OS	Yes	
OS Language	Yes	WP-523x-ML: Multi-language <ul style="list-style-type: none">- English- German- Russian- French- Spanish- Italian- Korean- Simplified Chinese- Traditional Chinese
.NET Compact Framework 3.5	Yes	V3.5.7283.0 for Visual Studio .Net 2008
SQL CE 3.5	Yes	SQL CE 3.5 (3.5.5386.0)
FTP Server	Yes	
HTTP Server	Yes	
Telnet	Yes	
Printer	No	
Display Resolution	Yes	1024*768, 800 * 600, 800*480, 640 * 480
Touch Panel	Yes	Support for touch panels using the RS-232 and USB interfaces
XV board 	Yes	Supported modules: <ul style="list-style-type: none">XV107 (8 DI, 8 DO)XV107i (8 DI, 8 DO)XV110i (16 DI)XV111i (16 DO)

Software and Hardware Compatibility

Software		Hardware	
OS	Eboot	V1.3 、 V1.4 、 V1.41 (256MB RAM)	V1.44 (512MB RAM)
V1.0.1.5 [03/20/2017] 512MB	V1.2.2.0	N/A	Yes
V1.0.1.5 [03/20/2017] 256MB	V1.2.2.0	Yes	N/A
V1.0.1.4 [03/10/2016] 512MB	V1.2.2.0	N/A	Yes
V1.0.1.4 [03/10/2016] 256MB	V1.2.2.0	Yes	N/A
V1.0.1.3 [11/26/2015] 256MB	V1.2.2.0	Yes	N/A
V1.0.1.2 [10/16/2015] 256MB	V1.2.2.0	Yes	N/A
V1.0.1.1 [05/20/2015] 256MB	V1.2.1.0	Yes	N/A

Determining the hardware version



Revision mark for PCB v1.4 and later.

Table of Contents

WP-523x OS 1.0.1.5 - Release Notes [03/20/2017]4

WP-523x OS 1.0.1.5 - Release Notes [03/20/2017]

Abstract

This release fixes an issue that occurred the user cannot get the correct system time tick when uses the GetTickCount().

Improvements and Bug Fixes

- Fixed an issue that occurred the user cannot get the correct system time tick when uses the GetTickCount().

Eboot 1.2.2.0 [10/20/2015]

- No change.

Software and Hardware Compatibility

軟體		硬體	
作業系統版本 [日期]	Eboot版本	V1.3、V1.4、V1.41 (256MB RAM)	V1.44 (512MB RAM)
V1.0.1.5 [03/20/2017] 512MB	V1.2.2.0	N/A	Yes
V1.0.1.5 [03/20/2017] 256MB	V1.2.2.0	Yes	N/A

WinPAC Utility and WinPAC SDK

- PACSDK DLL Version 4.4.0.4 (Released on 01/06/2017)
- PAC Utility Version 1.2.1.8 (Released on 09/09/2016)