# **Virtual CE Pro**

Quick Start Manual [Version 4.2]



1

# Warranty

All products manufactured by ICP DAS Inc. are warranted against defective materials for a period of one year from the date of delivery to the original purchaser.

# Warning

ICP DAS Inc. assumes no liability for damages consequent to the use of this product. ICP DAS Inc. reserves the right to change this manual at any time without notice. The information furnished by ICP DAS Inc. is believed to be accurate and reliable. However, no responsibility is assumed by ICP DAS Inc. for its use, or for any infringements of patents or other rights of third parties resulting from its use.

# Copyright

Copyright 1998-2006 by ICP DAS Inc., LTD. All rights reserved worldwide.

# **Trademark**

The names used for identification only maybe registered trademarks of their respective companies.

# License

The user can use, modify and backup this software on a single machine. The user may not reproduce, transfer or distribute this software, or any copy, in whole or in part.


ABOUT THIS MANUAL	4
1. INTRODUCTION	4
2. GETTING STARTED	6
2-1 INSTALLATION	6
2-2 REGISTRATION	7
2-3 RUNNING	7
3. FUNCTION OVERVIEW	
3-1 FUNCTIONS ON CLIENT (PC)	
3-1-1 Default Settings	
3-1-2 New Connection	
3-1-3 Connection Edit	
3-1-4 New Scenario	
3-1-5 Script Edit	
3-1-6 About	
3-2 FUNCTIONS ON SERVER (WINCON)	
3-2-1 Configure	
3-2-2 Disconnect	
3-2-3 Register	
3-2-4 About	
3-3 FUNCTIONS WHEN CONNECTING	
3-3-1 Configure	
3-3-2 File Explorer	
3-3-3 Edit	
3-3-4 Tools	
3-3-5 View	
4. APPLICATION	
4-1 GENERAL REMOTE CONTROL FROM CLIENT	
4-2 ACTIVE CONNECTION FROM SERVER	
4-3 DEBUGGING AND MAINTAINING	

3

# **About This Manual**

The manual is divided into four parts. The first part, 'Introduction', describes basic function and infrastructure of VCEP. The second part, 'Getting Started', describes installation, registration and running procedures step by step. The third part, 'Function Overview', describes all functions of VCEP. The fourth part, 'Application', describes different VCEP scenario in different application.

# **1. Introduction**



VCEP is designed for managing your WinCon-8000 anywhere. No matter where you are, VCEP provides a convenient environment on the Desktop PC and lets you control your WinCon-8000 remotely.

Virtual CE is composed of two main components: The 'Server' which runs on WinCon-8000 and the 'Client' which runs on a Desktop PC. Once a connection is established between the client and server (initiated by the client), the client will periodically send requests for screen updates and send mouse/key click information to the server to simulate. Each video frame is inter-compressed against the previous frame and then intra-compressed with a modified LZW scheme to minimize the amount of data transmitted from server to client.

	3	
Device	Minimum	Recommended
IBM compatible PC with	Pentium II	Pentium III
Pentium processor	350 MHz	500 MHz
System RAM	64 MB	128 MB
Hard disk	100 MB fr	ee memory space

#### HARDWARE REQUIREMENTS

#### SOFTWARE REQUIREMENTS

Microsoft Windows 2000 SP2 or Windows XP

#### MAIN FEATURES

- Save compressed AVI files
- Rotate the display to any angle in 90 degree increments
- Screen captures saved to BMP, GIF or JPG
- Copy clipboard contents to CE and back to PC
- Rapid data entry from your more comfortable PC mouse and keyboard
- 1-18 frames per second capture speed (depending on device and communication conduit)
- Support serial, Ethernet communications
- Minimal impact on target device CPU while capturing
- Auto-discovery of the target device on a LAN
- Works across the internet
- Capture screen shots to a BMP file or the clipboard
- Supports 2 + 4-bit monochrome and 8 + 16-bit color displays
- Scale image 1-4X
- Multiple instances of VCEP can run on the same PC allowing multiple devices to be controlled simultaneously
- > One-click capture of screen shots to BMP files with auto-naming
- Capture session to a standard AVI file for distribution
- Capture session keys/clicks for later playback
- Toggle toolbar display
- Toggle 'always-on-top' window feature
- > Paste text from the PC clipboard to the CE device
- Actively connect from Server to Client
- Watchdog auditing
- Record/Play script events


# 2. Getting Started

#### 2-1 Installation

- **Step 1:** Copy v\_remote.exe and WatchVCEP.exe from CD:\\VCEP\_4.2 folder to \CompactFlash\VCE of WinCon-8000.
- **Step 2:** Execute v\_remote.exe in WinCon-8000 and configure it as below then click OK. After setting password, don't forget to press 'Save an Reboot' button in WinCon Utility.

Configure LAN	
COM Port: COM1:	
Require a password for LAN	
Password: icpdas	
Connect to client	
Primary Client IP 61.62.70.78 Port 1901	
Secondary Client IP 59.125.116.157 Port 1901	
	Require a password for LAN     Password [ccpdas]     Connect to client     Primary Client IP 61.62.70.78 Port 1901

**Step 3:** Execute VCEP\_4.2.exe in CD:\\VCEP\_4.2 folder to install Virtual CE Pro Client to Desktop PC.



#### VCE Pro Quick Start Manual

**Step 4:** After that, you will find out Virtual CE Pro Client at 'Program File' as below.



# 2-2 Registration

**Step 1:** Click [File]->[Register] on WinCon-8000 for register as below.

File	Help	
Con	figure	
Disc	:onnect	
Sto	p ActiveSync	Vistual CE
Reg	jister	
Exit		
	Register	ок

Step2: Enter 'Register Code' of License into Register dialog and press OK.

#### ATTENTION! One Register Code only can be used in one WinCon-8000

#### 2-3 Running

Step 1: Make sure the v\_remote.exe is executed in WinCon-8000

Step 2: Select "Virtual CE Pro Client" from [Start]->[DAQPro]->[VCEP\_4.2] or execute "C:\DAQPro\VCE\_Pro\v\_ppc.exe"

	Script Window He Connections	*₽			Scripts	
Vame	Type	Port	Status	Name	Status	
WinCon-68	LAN (Auto		Idle	Nome -		

7

**Step 3:** Configure some basic settings at [File]->[Default Settings].

Refresh Rate 👖	) fps ု 🔘	Scale	1x 0
🖲 Show Skin	Skin:		C
3 16-color mode (	reduces data b	oy 50%)	
🔿 Queue events (	reduces LAN t	raffic)	
Accept inbound	d connections o	on port: 1	901
Screen Capture			
) File (	Clipboard	O One Cl	ick
Image file form	iat (one click):	BMP	0
Recording Meth	od		
Script events	: O AVI vide	eo   🔘 Shov	v Cursor
Script Dir: C:\D/	AQPro\VCE_P	ro\RECORD	Browse
			_

Step 4: Create a new connection.


Name:	WinCon-67	Window Background Color
Connection Type:	LAN (Auto Discovery)	Change
Target IP Address:	0.0.0.0	O Open Maximized
Port:	Refresh Rate: 10 fp	O Automatically connect at startup
Skin:	Scale: 1X O	C Low color mode
Screen Capture		O Queue Events
File O Clip Image file format (or	oboard O One Click ne click): BMP O	
Recording Method		ОК.
Script events	O AVI video 🛛 🔘 🤅	Show Mouse Cursor

**Step 5:** Press 'Connect' button. VCEP will automatically scan the available device within LAN.

<u>File</u> Connection <u>S</u> crip Co	: Window <u>H</u> elp N (Auto Discovery)	😑 pts
Name		Status
WinCon-67	Select one or more devices to c	connect to
	Device Name	IP Address
	WindowsCE	10.0.0.67
	< <u>-</u>	
	Scanning for devices	

**Step 6:** Enter your password and press 'OK' button.

	Password Required
	The selected device requires a password; please enter it in the space below.
	icpdas
	O Hide Password
	OK. Cancel
C	



Step 7: After that, you will see the screen of target device.

# **3. Function Overview**

VCEP function is divided into three parts. The first part describes functions on Client site. The second part describes functions on Server site. The third part describes functions when connecting.

# **3-1 Functions on Client (PC)**

All functions and settings at this section are on Client(PC) site.

#### 3-1-1 Default Settings

[File]->[Default Settings]

	De	efault Setting:	Ð	6
Refres	h Rate	10 fps 🔘	Scale	1x 🔘
) Sho	w Skin	Skin:		0
O 16-0	olor mode	e (reduces data	a by 50%)	
O Que	ue event:	s (reduces LAN	l traffic)	
) Acc	ept inbou	nd connection	s on port: 19	01
Scre	en Captur	re	L	
() F	file	O Clipboard	O One Clic	k
Im	age file fo	rmat (one click	): BMP	0
Reco	ording Met	thod		
🔘 S	cript ever	nts 🔿 AVI v	ideo 🛛 💿 Show	Cursor
Script [	Dir: C:M	DAQPro\VCE_	Pro\RECORD	Browse
	ж			ancel

**Refresh Rate:** High refresh rate requires high LAN traffic. 1fps ~18fps for option **Scale:** Display scale. 1x / 2x / 3x / 4x for option

16-color mode: Choosing this option can reduce data by 50%

Queue events: Choosing this option can reduce LAN traffic

**Screen Capture:** Choosing the method to capture screen and the format (BMP/BMP24/GIF/JPEG) to store

**Recording Method:** Choosing the method (Script/AVI) to record and showing cursor or not

Script Dir: The location to save script

#### 3-1-2 New Connection [Connection]->[New]

Name:	New Connection	Window Background Color
Connection Type:	IRDA	Change
Target IP Address:	0.0.0.0	O Open Maximized
Port:	Refresh Rate: 10 fps	O Automatically connect at startup
Skin:	Scale: 1X O	O Low color mode
Screen Capture		] O Queue Events
File O Cli Image file format (o	ipboard O One Click ne click): BMP O	
Recording Method		

#### Name: Any name

Connection Type: Choosing the type of connection (Serial / WAN / LAN / Connect From Server)

**Target Address:** The IP address of Server should be entered if choosing the type of 'WAN'

**Port:** Port means COM port if choosing the type of 'Serial'. Port means IP port which is the same with server if choosing the type of 'Connect From Server'

**Refresh Rate:** High refresh rate requires high LAN traffic. 1fps ~18fps for option. **Scale:** Display scale. 1x / 2x / 3x / 4x for option

Windows Background Color: Windows' background color

**Open Maximized:** Maximize the display when connecting

Automatically connect at startup: Connect to server automatically when startup Low color mode: Choosing this option can reduce data by 50%

Queue Events: Choosing this option can reduce LAN traffic

**Screen Capture:** Choosing the method to capture screen and the format (BMP/BMP24/GIF/JPEG) to store

**Recording Method:** Choosing the method (Script/AVI) to record and showing cursor or not

#### 3-1-3 Connection Edit



New: See '3-1-2 New Connection' Delete: Delete the connection in the list Edit: Edit old connection. See '3-1-2 New Connection' Connect: Start connecting to WinCon-8000

#### 3-1-4 New Scenario [Script]->[New]

Scenario Name:	New Scenar	io,	
C Log Results			Browse
Scenario Loop Co	unt: 1	Loop Delay (seconds):	0
Add	Remove		
	Down		
Script Loop Cour	nt:		
Script Loop Dela	y:	j [	
	2.8	7/41	
	e when com	olete	
<ul> <li>Suspend devic</li> <li>Reset device v</li> </ul>		_	OK.

#### Scenario Name: Any name

Log Results: Log the results of scenario operating Scenario Loop Count: The times of playing scenario Loop Delay: The delay time between scenario and scenario Add: Add a script Remove: remove a script Up: push a script up Down: pull a script down Script Loop Count: The times of playing scripts in scenario: Script Loop Delay: The delay time between script and script in scenario Disable video update: No update on Client site for reducing traffic load




Play/Pause: Play/Pause the scenario in the list

Stop: Stop playing the scenario in the list

### 3-1-6 About

[Help]->[About VCE...] Show version message.



### **3-2 Functions on Server (WinCon)**

All functions and settings at this section are on WinCon-8000.

# 3-2-1 Configure

[File]->[Configure...]

Configure LAN	-
COM Port: COM1;	
Require a password for LAN	
Password: icpdas	
Connect to client	
Primary Client IP 61.62.70.78	Port 1901
Secondary Client IP 59.125.116.157	Port 1901
Retry Cycle <mark>5 sec.</mark>	
Activate Watchdog	

**Connection Type:** Choosing an appropriate 'Connection Type' (Serial / LAN / WAN) depends on WinCon-8000's real situation

**COM Port:** COM port number if choosing connection type of 'Serial' **Require a password for LAN:** Password for Ethernet connection from Client **Connect to client:** When WinCon-8000 is in LAN and Client is in WAN with public IP, you can check this and assign two Client IP for active connection from WinCon-8000. If the first Client IP can not be connected to, VCEP will connect to second Client IP automatically. If the connection of the first Client IP restore, you have to disconnect the second connection manually to connect to the first one. The 'Retry Cycle' means the time between two connections **Active Watchdog:** This function can let VCEP restore automatically if VCEP

crash for un-known reason


#### 3-2-2 Disconnect

[File]->[Disconnect] Disconnect the connection from server site.




# 3-2-3 Register

[File]->[Register] Register dialog for registration. If you don't register, VCEP works under trial version of 5 minutes.



#### 3-2-4 About

[Help]->[About...] Show version message.



# **3-3 Functions when Connecting**

When connecting, you can see some functions upper the window. These function descriptions are as below.

File	Edi	t <u>T</u> oo	ls <u>V</u>	iew		
<b>(</b> )	<b>8</b>	<u>。</u>	•		3	

3-3-1 Configure [File]->[Configure...] See '3-1-1 Default Settings'

	Configure		
Refresh Rate	10 fps	Scale	1x
🖲 Show Skin	Skin:		
0 16-color mo	de (reduces data l	by 50%)	
Queue ever	nts (reduces LAN t	traffic)	
Accept inbo	und connections	on port:	
Screen Capt	ure	·	
Sile File	O Clipboard	O One Clie	ck
Image file	format (one click):	ВМР	0
Recording M	lethod		
Script ev	ents 🛛 🔿 AVI vid	eo 🔿 Show	/ Curso
Script Dir:			Brow
schpebil.			Corows
10			

#### 3-3-2 File Explorer [File]->[File Explorer]

		VCE File Explorer	- ICPDAS Device		
My Computer 🔻		💼 🛛 Name 🔻	→ My Device ▼	Ē	Name 🔻
Name	Size	Date	Name         CompactFlash         My Documents         Programs         Programs         Recycled         Temp         Windows         Control Panel Ink         DCONCE.dll         Wincon.dll	Size 23B 100.0K 52.0K	Date

Left side of window shows the file tree on PC. Right side of window shows the file tree on WinCon-8000. You can transfer files by clicking the buttons between two windows.

#### 3-3-3 Edit [Edit]



Paste to device: This function allows you paste text from PC to WinCon-8000 Capture to Clipboard: Capture the screen and save it into clipboard. After capturing to clipboard, you can paste the image to any application program Capture to File...: Capture the screen and save in file Capture (One Click): Capture the screen to be file in 'Script Dir' folder

#### 3-3-4 Tools [Tools]



Start Recording: Start recording according to the settings in '3-1-1 Default Settings'

**Stop Recording:** Stop recording according to the settings in '3-1-1 Default Settings'

Soft Reset: Soft-reset WinCon-8000

3-3-5 View [View]




**Device Info...:** Show WinCon-8000 information **Process Info...:** Show process information of WinCon-8000 **Refresh Display:** Refresh display once when using this function **Scale:** Change the display scale (1x / 2x / 3x / 4x)**Rotate:** Rotate display  $(0^{\circ} / 90^{\circ} / 180^{\circ} / 270^{\circ})$ 

# 4. Application

This section describes how to set VCEP in different scenario step by step. 4-1 General Remote Control from Client

Generally speaking, VCEP will be applied when PC and WinCon-8000 are all in LAN (See Figure 1) or in WAN (See Figure 2). This section highlights some important settings and reminds you of functions in common use.

#### VCE Pro Quick Start Manual



Step 1: Refer to '2-2 Running' and connect PC and WinCon-8000. The setting of 'Connection Type' in '2-2 Running' depends on the real situation. If PC and WinCon-8000 are all in WAN, you have to set IP address

Step 2: You can adjust 'Color Mode', 'Queue Events' and 'Refresh Rate' to reduce traffic load.


Step3: You can check 'Active Watchdog' in '3-2-1 Configure'. This function can let VCEP restore automatically if VCEP crash for un-known reason.

Step4: Though WinCon-8000 supports FTP itself, you can use '3-3-2 File Explorer' function of VCEP to transfer files between PC and WinCon-8000 as well.

Step5: Finally, don't forget these convenient functions of 'Screen Capture' of '3-3-3 Edit' and 'Recording Script/AVI' of '3-3-4 Tools'.

#### 4-2 Active Connection from Server

In some situation, WinCon-8000 only has private IP in LAN, but has to communicate with PC in WAN (See Figure 3). At this kind of situation, you have to use 'Connect to client' in '3-2-1 Configure'. You can check this and assign two 'Client IP' for active connection from WinCon-8000. If the first 'Client IP' can not be connected to, VCEP will connect to second 'Client IP' automatically. If the connection of the first 'Client IP' restore, you have to disconnect the second connection manually to connect to the first one. The 'Retry Cycle' means the time between two connections





Step 1: Enter appropriate variables in 'Connect to client'.

**Step 2:** Refer to '3-1-2 New Connection' and create a new connection on PC. Choose 'Connect from server' in 'Connection Type'. The 'Port number' should be the same with the 'Port number' at **Step 1**.

**Step 3:** Press the 'Connect' button and have patient waiting the connection from WinCon-8000.

**Step 4:** After successful connection, you can refer to '4-1 General Remote Control from Client' for all activities on WinCon-8000.

#### 4-3 Debugging and Maintaining

VCEP 4.2 allows user recording and playing script. This function is very convenient to debug and maintain WinCon-8000. For example, user can re-play a script to re-generate the problem for debugging. Also, user can record a script for registration which can simplify the procedure of deploying application to different WinCon-8000.

#### [Recording]

Step 1: Choose 'Script Events' of 'Recording Method' in 'New Connection' dialog

**Step 2:** Refer to '4-1 General Remote Control from Client' and connect to WinCon-8000

Step 3: Choose [Tools]->[Start Recording] to record all activities when connecting

Step 4: Choose [Tools]->[Stop Recording] to stop recording and save in file

#### [Playing]

**Step 1:** Refer to '3-1-4 New Scenario' and create a scenario. If you check 'Log Results', the log file will record all results when playing scenario. If you have several scripts should be played in one scenario, you can add all of them in the list by 'Add' function and set loop for each one. If the activities in scenario do not need to see on PC, remember to check 'Disable Video Update'.

Step 2: Choose one WinCon-8000 to connect

**Step 3:** After press 'Play' button, you will see a 'Run Script' dialog. Choose the WinCon-8000 and 'Run'. Now, you can find out WinCon-8000 act as you record before