Classification	System and Ap	plication F	AQ on WinCE	PAC		No.	1-009-02
Author	Tunglu-Yu	Version	1.0.0	Date	2010/2/12	Page	1/4

How to change the display type for WP-8x3x

opli	ies to:		
	Platform	OS version	WinPAC/ViewPAC utility version
	WP-8x3x	All versions	All versions
	WP-8x4x	N/A	N/A
	VP-25W1	N/A	N/A
	VP-23W1	N/A	N/A

N/A: Not applicable to this platform and OS.

Tips & Warnings



A

If your monitor doesn't support the display mode that you set, the monitor may not display correctly.

The default display resolution for WP-8x3x is "1024*768". To change the display mode for WP-8x3x, perform the following steps:

Step 1: Change the display resolution.

Start the WinPAC Utility on the desktop, select the display resolution and click the setting button below the Frequency column.

WinPAC Utility [2.0.1.5]	
File Help Configuration	
System Setting Ithernet Setting FTP	Setting System Information Auto Execution Multi-serial port Welcome to use WinPAC Utility This tool will help you to set WinPAC - 8000. Display Resolution : 1024 * 768 Bpp : 320 * 240 640 * 480 800 * 600 Tog4 * 768 Setting
Battery1 : OK Battery2 : OK Change HTTP document root directory \ \windows\www\wwwpub\	Task Bar Setting: Auto Hide Always On Top windows\www\wwwpub to: Setting
	AS Co. Ltd Technical decomment

Classification	System and Ap	plication F	AQ on WinCE	PAC		No.	1-009-02
Author	Tunglu-Yu	Version	1.0.0	Date	2010/2/12	Page	2/4

WinPAC Utility [2.0.1.5]	
File Help Configuration	
System Setting Ethernet Setting FTP 9	Setting System Information Auto Execution Multi-serial port
WinPAC WinPAC Industrial Control Products Data Acquisition System	Welcome to use WinPAC Utility This tool will help you to set WinPAC - 8000. Display Resolution : 800 * 600 Bpp : 16 Frequency : 60 Setting
Battery1 : OK	Task Bar Setting: 🔄 Auto Hida 🔽 Alway 🖓 Top
Battery2: OK	Empty Desktop
Change HTTP document root directory \\	\windows\www\wwwpub to:
\windows\www\wwwpub\	Setting

Step 2: Save and Reboot your WinPAC.

- 2.1. Click "File" → "Save and Reboot".
- 2.2. Click the "Yes" button and wait for the device to reboot.

WinPAC Utility [2.0.1.] File Help Configuration Save Save Save	4] ation
Rebeet <u>Without Gave</u> Restore Default Setting E <u>x</u> it	Warning U × Would you like to save the setting and reboot the device ?

Classification	System and Ap	plication F	AQ on WinCE	PAC		No.	1-009-02
Author	Tunglu-Yu	Version	1.0.0	Date	2010/2/12	Page	3/4

Tips & Warnings

If nothing displayed on your monitor while booting, the display settings selected on the WP-8x3x may not be supported by your monitor.

Please see the document "**W1-009-04**: How to change the display type for WP-8x3x when display out of range" for more details.

Classification	System and Ap	plication F	AQ on WinCE	PAC		No.	1-009-02
Author	Tunglu-Yu	Version	1.0.0	Date	2010/2/12	Page	4/4

Revision History

Revision	Date	Description		
1.0.0	2010/02/12	Initial release		