
Classification	System and Ap	No.	2-015-00				
Author	Tunglu-Yu	Version	1.0.0	Date	2013/5/16	Page	1/3

How to change the language for the User Interface and the Input Method Editor

Applies to:						
	Platform	OS version	WinPAC/ViewPAC utility version			
	WinPAC series	All versions	All versions			
	ViewPAC series	All versions	All versions			


The WinCE support "Multilingual User Interface" (MUI) and "Input Method Editor" (IME). You can change the language for the user interface and IME by perform follow step.

Step 1: Double click the icon for Regional Settings in the Control Panel and then click the Language tab to select the User Interface Language.




Classification	System and Ap	No.	2-015-00				
Author	Tunglu-Yu	Version	1.0.0	Date	2013/5/16	Page	2/3

Step 2: Click the Input tab and the check the input language you wish to use. The default language when you start your device is set in the input tab, too.



Step 3: Execute the WinPAC_utility and select the "Save and Reboot" option.



OS version and supported languages

OS vers	sion	English	German	Russian	French	Spanish	Italian	Korean	Simplified Chinese	Traditional Chinese
V1502	EN	Δ	0	0	0	0	0			
and earlier	TC	0								Δ
ournor	SC	0							Δ	
V1601	EN	Δ	0	0	0	0	0	0		
and later	TC	0								Δ
, aco	SC	0							Δ	

 \triangle : The default user interface language in the OS.

O: The language for both the UI and the IME the OS supported.

ICP DAS Co., Ltd. Technical document

Classification	System and Ap	No.	2-015-00				
Author	Tunglu-Yu	Version	1.0.0	Date	2013/5/16	Page	3/3

Revision History

Revision	n Date	Description	
1.0.0	2013/05/16	Initial release	