

Classification	System and Application FAQ on XPAC				No.	2-004-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/23	Page	1/6

How to edit the registry

Applies to:

<i>Platform</i>	<i>OS version</i>	<i>XPAC utility version</i>
<i>XPAC series</i>	<i>All versions (WinCE6)</i>	<i>All versions</i>

Tips & Warnings



Editing the registry may result in unexpected errors.

To edit the registry, perform the following steps:

Step 1: Find the regedit.exe files

The “regedit.exe” file is located at

1. The “\System_Disk\Tools\ReEdit” folder on the XPAC device.
2. ftp://ftp.icpdas.com/pub/cd/xp-8000-ce6/system_disk/tools/regedit/ (XP-8000-CE6)
ftp://ftp.icpdas.com/pub/cd/xpac-atom-ce6/system_disk/tools/regedit/ (XP-8000-Atom-CE6)

Step 2: Edit the registry.

2.1. Double click the Regedit.exe icon.



2.2. Select the key or value you want to edit.

Classification	System and Application FAQ on XPAC					No.	2-004-00
Author	Weikai	Version	1.0.0	Date	2011/3/23	Page	2/6

File Help

Name	Type	Data
RotarySwitch0	String	Normal Mode
RotarySwitch1	String	Safe Mode
RotarySwitch2	String	
RotarySwitch3	String	
RotarySwitch4	String	
RotarySwitch5	String	
RotarySwitch6	String	
RotarySwitch7	String	
RotarySwitch8	String	\System_Disk\Tools\DCON_CE\DCON_CE_XP.exe
RotarySwitch9	String	\System_Disk\Tools\Remote_Display\cerdisp.exe
test	String	1234
XPAC_CE_OS...	String	1.0.0.0

Key (points to ICPDAS in the left tree)

Value (points to test in the table)

2.3. Edit the value you want.

2.3.1. Double click the value you want to edit.
 Enter the value and then click the "OK" button.

Edit Registry Key

Value Name:

Value Data:

Ok Cancel

Enter the value you want to edit. (points to the Value Data field)

2.4. Add a new sub key or value.

2.4.1. Go to the "Path" where you want to add a new sub key or value.


File Help

Name	Type	Data
RotarySwitch0	String	Normal Mode
RotarySwitch1	String	Safe Mode
RotarySwitch2	String	
RotarySwitch3	String	
RotarySwitch4	String	
RotarySwitch5	String	
RotarySwitch6	String	
RotarySwitch7	String	
RotarySwitch8	String	\System_Disk\Tools\DCON_CE\DCON_CE_XP.exe
RotarySwitch9	String	\System_Disk\Tools\Remote_Display\cerdisp.exe
test	String	1234
XPAC_CE_OS...	String	1.0.0.0


ICPDAS (circled in the left tree)

Classification	System and Application FAQ on XPAC					No.	2-004-00
Author	WeiKai	Version	1.0.0	Date	2011/3/23	Page	3/6

2.4.2. Move mouse to right space, and then click mouse-right. Select menu option “Add” to add key or value.




2.4.2.1. Add a new key. Select “key” and then click mouse-left button. Key in the key name and then click “ok” button.



Classification	System and Application FAQ on XPAC					No.	2-004-00
Author	WeiKai	Version	1.0.0	Date	2011/3/23	Page	4/6

2.4.2.2 Select new Value type


Select in the value type and then click mouse-left button to show menu option.



2.4.2.3. Add a new Value.



Key in the value name and value, and then click “ok” button.

Classification	System and Application FAQ on XPAC				No.	2-004-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/23	Page	5/6




2.5. Delete a key or value.

Click the key or value you want to delete, and then click mouse-right button to show menu option.



(Status of delete Sub key)

Classification	System and Application FAQ on XPAC				No.	2-004-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/23	Page	6/6



(Status of delete value)

