

Classification	Development FAQ on XPAC				No.	5-002-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/21	Page	1/5

## How to debug the XPAC programs in Visual Studio 2005/2008 online through the TCP/IP

Applies to:

Platform	OS version	XPAC utility version
XPAC series	All versions (WinCE6)	All versions

To debug XPAC programs in Visual Studio 2005/2008 online, perform the following steps:

### Tips & Warnings



You must install the XPAC SDK before you can develop any programs. The XPAC SDK is a Software Development Kit (SDK) that contains C header files, C libraries and other documents. Below is the step-by-step procedure for installing the XPAC SDKs.

Step 1: Insert the CD into your CD-ROM drive

Step 2: Execute the "XPacSDK\_CE\_n.n.n.msi" which is located in  
CD:\SDK\PlatformSDK

Step 3: Follow the prompts until the installation is complete

**Step 1: Make sure** the following files are listed together with the matching version numbers.


Path	File
C:\Program Files\Common Files\Microsoft Shared\CoreCon\1.0\Bin	1. ActiveSyncBootstrap.dll 2. ConMan2.dll 3. ConManPS.dll 4. DesktopDMA.dll 5. eDbgTL.dll 6. TcpConnectionC.dll
C:\Program Files\Common Files\Microsoft Shared\CoreCon\1.0\Bin\1033	conmanui.dll
C:\Program Files\Common Files\Microsoft Shared\CoreCon\1.0\Target\wce400\armv4i	1. DeviceDMA.dll 2. eDbgTL.dll 3. TcpConnectionA.dll 4. clientshutdown.exe 5. CMAccept.exe 6. ConmanClient2.exe

Classification	Development FAQ on XPAC				No.	5-002-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/21	Page	2/5


**Step 2:** If the version number matches correctly and all the files are there, copy the following files to the XPAC side:

Clientsshutdown.exe, ConmanClient2.exe, CMaccept.exe, eDbgTL.dll, TcpConnectionA.dll

**Step 3:** Click the “Project-> [Project Name] Properties...” menu option.




**Step 4:** On the “Devices\*” tab, deselect “Deploy the latest version of the .NET compact Framework (including Service Packs)” check box.




Classification	Development FAQ on XPAC				No.	5-002-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/21	Page	3/5

**Step 5:** Click the “Device Options” icon on the toolbar.




**Step 6:** Select the “XPacSDK\_CE” from the “Show devices platform” list, and then click the “Properties...” button. In the properties dialog window, click the configure button and then enter the IP address of the target device in the “use specific IP address” field in the “Configure TCP/IP Transport” dialog. Click “OK” on all open dialogs.




Classification	Development FAQ on XPAC				No.	5-002-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/21	Page	4/5

**Step 7: Execute** both the “CommanClient2.exe” and the “CMAccept.exe” applications on the WinPAC.



**Step 8: Click** “Connect to Device” icon on the toolbar.



**Step 9: Wait** for the connection to be established.



**Step 10: After the Connection is established, you can debug the program online.**

Classification	Development FAQ on XPAC				No.	5-002-00	
Author	WeiKai	Version	1.0.0	Date	2011/3/21	Page	5/5

**FAQ:**

- ⚠ If the connection fails, as shown below, return to step 6 to perform the following actions.

